

XPS snapshot compatibility

Release note of the 28th June 2022

Latest modifications added on the new XPS controller revisions involved a snapshot compatibility break. New snapshot cannot be installed on previous controller versions and previous snapshots cannot be installed on latest controllers.

See below details on snapshot compatibilities.

- XPS-D
 - **Serial number \geq 22308106**
 - These controllers are compatible with snapshot **XPS-D-131xx**.
 - **Serial number \leq 22308105**
 - These controllers are compatible with snapshot **XPS-D-N130xx**.
- XPS-RLD
 - **Serial number \geq 22348036**
 - These controllers are compatible with snapshot **XPS-D-161xx**.
 - **Serial number \leq 22304035**
 - These controllers are compatible with snapshot **XPS-D-N160xx**.
- HXP-D
 - HXP50-D
 - **Serial number \geq 22362019**
 - These controllers are compatible with snapshot **XPS-D-501xx**.
 - **Serial number \leq 22362018**
 - These controllers are compatible with snapshot **XPS-D-N500xx**.
 - HXP100-D
 - **Serial number \geq 22363008**
 - These controllers are compatible with snapshot **XPS-D-501xx**.
 - **Serial number \leq 22363007**
 - These controllers are compatible with snapshot **XPS-D-N500xx**.

- HXP100P-D
 - **Serial number \geq 21364002**
 - These controllers are compatible with snapshot **XPS-D-501xx**.
 - **Serial number \leq 21364001**
 - These controllers are compatible with snapshot **XPS-D-N500xx**.
- HXP200-D
 - **Serial number \geq 22365006**
 - These controllers are compatible with snapshot **XPS-D-501xx**.
 - **Serial number \leq 22365005**
 - These controllers are compatible with snapshot **XPS-D-N500xx**.
- HXP200S-D
 - **Serial number \geq 22366002**
 - These controllers are compatible with snapshot **XPS-D-501xx**.
 - **Serial number \leq 22366001**
 - These controllers are compatible with snapshot **XPS-D-N500xx**.
- HXP1000-D
 - **Serial number \geq 22367002**
 - These controllers are compatible with snapshot **XPS-D-501xx**.
 - **Serial number \leq 22367001**
 - These controllers are compatible with snapshot **XPS-D-N500xx**.

If you try to install a snapshot that is not compatible with your controller, the installation will be aborted, and the controller will return to its pre-installation state.

The support of previous generation's snapshots (**130xx**, **160xx** and **500xx**) will continue but they will not be enhanced with new features.